

# pfSense Firewall

Configuration and How-to's for pfSense Firewall

- [Basics](#)
  - [Accessing pfSense: SSH, Web Interface, and Serial Console](#)
- [VPN](#)
  - [OpenVPN Site-to-Site Configuration Example with SSL/TLS](#)
  - [OpenVPN Remote Access Configuration Example](#)
- [HaProxy](#)
  - [T-RMM-PFSense-HAProxy-config](#)
  - [How to Configure HAProxy for Docker-based Nextcloud AIO](#)

# Basics

Basic Information on the pfSense Firewall

# Accessing pfSense: SSH, Web Interface, and Serial Console

1200px-PfSense\_logo.png

In this tutorial, we'll guide you through three methods of accessing your pfSense firewall: SSH, the web interface, and the serial console. We'll be using MobaXterm, a versatile remote computing tool, to simplify the process.

## 1. Accessing pfSense via SSH:

SSH allows secure remote access to your pfSense system's command-line interface. Here's how to do it:

1. Open MobaXterm on your computer.
2. Click on the "Session" button in the top-left corner.
3. In the "Session settings" window:
  - Choose "SSH" as the protocol.
  - Enter the IP address or DNS name of the pfSense firewall in the "Remote host" field.
  - Set the "Port" to the SSH port (typically 22).
  - Enter your pfSense username tied to the MSLS Partners AD Domain.
  - Choose "Use private key" if applicable, or use "Password" and enter your password.
4. Click the "OK" button.
5. Double-click the SSH session in the main MobaXterm window to open the SSH terminal.

## 2. Accessing pfSense via Web Interface:

The web interface provides a graphical way to manage your pfSense settings. Follow these steps to access it:

1. Open a web browser on a computer connected to the local network.
2. Enter the IP address or DNS name of the pfSense firewall in the address bar. For example:
  - IP address: `https://192.168.100.1:9443`
  - DNS name: `https://firewall-1.ms lspartners.com:9443`

3. If you encounter a security warning due to the SSL certificate, proceed to the site (or add an exception).
4. On the login page, enter your pfSense credentials:
  - Username: Your MSLS Partners AD Domain username
  - Password: Your corresponding password
5. Click "Login" to access the pfSense web interface.

### **3. Accessing pfSense via Serial Console:**

The serial console is an important method for direct access to your pfSense system. Here's how to connect using MobaXterm:

1. Connect a serial cable between your computer and the pfSense serial console port.
2. Open MobaXterm on your computer.
3. Click on the "Session" button in the top-left corner.
4. In the "Session settings" window:
  - Choose "Serial" as the protocol.
  - Select the correct COM port corresponding to your serial connection.
  - Set the "Baud rate" to 115200 (default for pfSense).
  - Ensure "Data bits" is set to 8, "Parity" to None, and "Stop bits" to 1 (8N1).
5. Click the "OK" button.
6. Double-click the serial session in the main MobaXterm window to open the console.

That's it! You now know how to access pfSense using SSH, the web interface, and the serial console using MobaXterm. These methods offer you different levels of access and control for managing your pfSense firewall.

Remember to use the appropriate credentials and settings based on your pfSense configuration. If you encounter any issues, please reach out for assistance.

# VPN

How-to's and Configuration guides for pfSense VPN

# OpenVPN Site-to-Site Configuration Example with SSL/TLS

## OpenVPN Site-to-Site Configuration Example with SSL/TLS

A site-to-site connection using **SSL/TLS** in client/server mode is convenient for managing a large number of remote sites connecting back to a central site in a hub-and-spoke fashion.

## Example Configuration Overview

[/images/diagrams/openvpn-site-to-site-ssl\\_tls.png](#)

OpenVPN Example Site-to-Site SSL/TLS Network

When configuring a site-to-site OpenVPN connection using SSL/TLS one firewall will be the server and the others will be clients.

### Tip

Usually the main location will be the server and the remote offices will act as clients, though if one location has a static IP address and more bandwidth than the main office that may be a more desirable location for the server.

This style of VPN requires a dedicated subnet for the OpenVPN interconnection between networks in addition to the subnets on both ends. Figure [OpenVPN Example Site-to-Site SSL/TLS Network](#) shows a depiction of this layout, using 10.3.101.0/24 as the IPv4 VPN Tunnel Network. This can be any subnet so long as it does not overlap another subnet currently in use on the network.

OpenVPN allocates IP addresses the same way it does for remote access clients. When using a **Topology** style of *subnet*, each client obtains one IP address in a common subnet. When using a **Topology** style of *net30*, each connecting client gets a /30 subnet to interconnect itself with the server.

See also

The *subnet* topology style uses address space more efficiently and has less quirks with its behavior in general, but certain very old clients may not be compatible. See [Topology](#) for more details.

The following sections describe how to configure the server and client sides of the connection.

# Example Configuration Settings

OpenVPN Endpoint Settings - Site A - Server

Site A - Server	
Name	Austin Office
WAN Address	198.51.100.3
LAN Subnet	10.3.0.0/24
LAN Address	10.3.0.1
CA Name	S2SCA
Cert CN	serverA
Tunnel Net	10.3.101.0/24

OpenVPN Endpoint Settings - Site B - Client

Site B - Client	
Name	London Office
Cert CN	clientB
WAN Address	203.0.113.5
LAN Subnet	10.5.0.0/24

Site B - Client	
LAN Address	10.5.0.1

#### OpenVPN Endpoint Settings - Site C - Client

Site C - Client	
Name	Colorado Office
Cert CN	clientC
WAN Address	198.51.100.7
LAN Subnet	10.7.0.0/24
LAN Address	10.7.0.1

# Configuring SSL/TLS Server Side

The server **requires** two items to reach the networks behind each client:

- A `route` to tell the operating system that OpenVPN knows about a remote network
- An internal route (`iroute`) in an OpenVPN Client-Specific Override to tell OpenVPN how to route that subnet to a specific client certificate

More detail on this will follow in the example.

See also

- [Client Specific Overrides](#)
- [Troubleshooting OpenVPN Internal Routing \(iroute\)](#)
- [Tunnel Settings](#)

## Create Certificate Structure

The first step is to create a certificate structure for this VPN.

This example uses the names listed in [Example Configuration Settings](#) – The CA is named `S2SCA`, the Server CN is named `serverA`, and the clients are `clientB` and `clientC`.

See also

## Create a Certificate Authority

Create a CA unique to this VPN:

- Navigate to **System > Cert Manager, CAs** tab
- Click **Add** to create a new a CA
- Enter the settings as follows:

Descriptive Name

S2SCA

Method

*Create an internal Certificate Authority*

Randomize Serial

*Checked*

Key Type

*RSA, 2048 (or higher)*

Digest Algorithm

*sha256 (or higher)*

Lifetime (days)

3650

Common Name

S2SCA

Subject Component Fields

The remaining fields are optional, but can be set to reflect the location of the CA.

- Click **Save**

## Create a Server Certificate

Create a server certificate signed by the VPN CA:

- Navigate to **System > Cert Manager, Certificates** tab
- Click **Add** to create a new certificate
- Enter the settings as follows:

Method

*Create an internal Certificate*

Descriptive Name

serverA

Certificate Authority

S2SCA

Key Type

*RSA, 2048 (or higher)*

Digest Algorithm

*sha256* (or higher)

Lifetime (days)

398

Note

Some current operating systems and software limit server certificates to a maximum lifetime of 398 days for security reasons. Clients on these platforms may reject a server certificate with a longer lifetime.

Common Name

serverA

Subject Component Fields

The fields contain data copied from the CA and are optional, but can be set to reflect the location of the server.

Certificate Type

*Server Certificate*

Warning

This setting is critical, do not forget to set this value.

Alternative Names

Optional extra entries, if needed, which specify alternate ways to identify the server. This can be left blank if the certificate will only be used by OpenVPN. Otherwise, add fields with additional information such as alternate hostnames, static IP addresses, and so on which are relevant to this server.

- Click **Save**

## Create User Certificates

Create user certificates for each remote site signed by the VPN CA.

- Navigate to **System > Cert Manager, Certificates** tab
- Click **Add** to create a new certificate
- Enter the settings as follows:

Method

*Create an internal Certificate*

Descriptive Name

clientB

Certificate Authority

S2SCA

Key Type

*RSA, 2048* (or higher)

Digest Algorithm

*sha256* (or higher)

Lifetime (days)

3650

Common Name

clientB

### Subject Component Fields

The fields contain data copied from the CA and are optional, but can be set to reflect the location of the client.

### Certificate Type

*User Certificate*


### Warning

This setting is critical, do not forget to set this value.

### Alternative Names




Optional extra entries which specify alternate ways to identify the client. These can be left blank if the certificate will only be used by OpenVPN. Otherwise, add fields with additional information such as alternate hostnames, static IP addresses, and so on which are relevant to this client.

- Click **Save**

Repeat this process for every client (e.g.  and any future clients).

## Export Certificates


The next task is to export the certificates and keys which the client requires when connecting to the OpenVPN server.

- Navigate to **System > Cert Manager, CAs** tab
- Click  on the row for the CA to export its certificate
- Navigate to **System > Cert Manager, Certificates** tab
- Click  on the row for each client certificate to export the certificates
- Click  on the row for each client certificate to export the private key for the client certificates.

### Warning

**Do not** export the CA key, server certificate, or server key. The client does not need these and copying them unnecessarily significantly weakens the security of the VPN.

## Configure the OpenVPN Server Instance

- Navigate to **VPN > OpenVPN, Servers** tab
- Click  **Add** to create a new server
- Fill in the fields as described below, with everything else left at defaults.  
Use values appropriate for this network, or the defaults if unsure.

See also

See [Server Configuration Options](#) for details on each of these options.

Description

Enter text to describe the connection, e.g. .

Server Mode

*Peer to Peer (SSL/TLS)*

DCO (Plus Only)

Check this box to activate the [OpenVPN Data Channel Offload \(DCO\)](#) feature for the server if desired.

See also

See [OpenVPN Data Channel Offload \(DCO\)](#) for additional information.

Device Mode

*tun*

Protocol

*UDP on IPv4 only*

Interface

*WAN*

Local Port

TLS Configuration

Check the **Use a TLS Key** box to enable TLS authentication which provides protection for the tunnel control channel.

Leave **Automatically generate a TLS Key** checked so the firewall will generate a new key automatically the first time this entry is saved.

Peer Certificate Authority

Select the CA created at the beginning of this process ()

Peer Certificate Revocation List

Select a CRL for the CA, if one exists.

Server Certificate

Select the server certificate created at the beginning of this process ()

IPv4 Tunnel Network

Enter the chosen tunnel network,

IPv4 Local Network(s)

Enter the LAN subnets for all sites including the server:

Note

If there are more networks on the server side that clients need to reach, such as networks reachable via static routes, other VPNs, and so on, add them as additional entries in the **IPv4 Local Network** box.

IPv4 Remote Network(s)

Enter **only** the client LAN subnets:

Inactive

☐ to disable disconnecting idle clients, so that site-to-site connections can stay up indefinitely.

- Click **Save**.
- Click **fa-pencil** to edit the new server instance
- Find the **TLS Authentication** box
- Select all of the text inside
- Copy the text to the clipboard
- Save this to a file or paste it into a text editor such as Notepad temporarily

## Create Client-Specific Overrides

Now add **Client Specific Overrides** for each client site. These tie a client subnet to a particular certificate so that OpenVPN can properly route a subnet to the correct site.

- Navigate to **VPN > OpenVPN, Client Specific Overrides** tab
- Click **fa-plus** to add a new override
- Fill in the fields on this screen as follows:

Common Name

Enter the CN of the first client site. In this example, that is .

IPv4 Remote Network/s

The clientB LAN subnet, .

Note

This field sets up the internal route ()

- Click **Save**

Add an override for the second site, adjusting the **Common Name** and **IPv4 Remote Network** to match. In the example for site C, these values would be  and  respectively.

See also

- [Client Specific Overrides](#)
- [Troubleshooting OpenVPN Internal Routing \(iroute\)](#)
- [Tunnel Settings](#)

## Firewall Rules

### External Traffic (WAN)

Next, add a firewall rule for the WAN interface which allows access to the OpenVPN server.

- Navigate to **Firewall > Rules, WAN** tab
- Click **fa level-up** and or **Add to create** a new rule at the top of the list
- Set the options as follows:

Protocol

*UDP*

Source

*any* (since multiple sites must connect)

Tip

For extra security, if the clients have static IP addresses, create an alias containing these addresses, then set it as the source on this rule.

Destination

*WAN Address*

Destination port

Description

- Click **Save**
- Click **Apply Changes**

## Tunneled Traffic

Now add a rule to the **OpenVPN** tab to pass traffic over the VPN from the Client-side LAN to the Server-side LAN. This can be an “Allow all” style rule or a set of stricter rules. This example allows all traffic using this rule:

- Navigate to **Firewall > Rules, OpenVPN** tab
- Click **fa level-up** and or **Add to create** a new rule at the top of the list
- Set the options as follows:

Protocol

*any*

Source

*any*

Tip

For extra security, create an alias containing only the remote hosts or subnets which must initiate contact with hosts on the sever LAN, then use that alias as the source on this rule.

Destination

*any*

Tip

For extra security, create an alias containing only the local hosts or subnets on the server LAN which must accept connections from remote hosts across the VPN, then use that alias as the destination on this rule.

Description

- Click **Save**
- Click **Apply Changes**

That completes the server setup, next, now move on to configure the clients.

# Configuring SSL/TLS Client Side

## Import CA and Certificate

On the client, import the CA certificate along with the client certificate and key for that site. This is the same CA and client certificate created earlier in this document.

See also

[Certificate Management](#)

Import these items at **System > Cert Manager**.

First import the CA:

- Navigate to **System > Cert Manager, CAs** tab
- Click **Add** to create a new certificate authority
- Enter the settings as follows:

Descriptive Name

S2SCA

Method

*Import an existing Certificate Authority*

Certificate Data

Open the CA certificate file in a text editor on the client PC, select all of the text, and copy it to the clipboard. Then paste it into this field.

- Click **Save**

Next, import the client certificate:

- Navigate to **System > Cert Manager, Certificates** tab
- Click **Add** to create a new certificate
- Enter the settings as follows:

Method

*Import an existing Certificate*

Descriptive Name

clientB VPN Certificate

Certificate Type  
*X.509 (PEM)*

Certificate Data

Open the client certificate file in a text editor on the client PC, select all of the text, and copy it to the clipboard. Then paste it into this field.

Private Key Data

Open the client certificate private key in a text editor on the client PC, select all of the text, and copy it to the clipboard. Then paste it into this field.

- Click **Save**

Repeat these steps on each client firewall.

## Configure the OpenVPN Client Instance

After importing the certificates, create the OpenVPN client:

- Navigate to **VPN > OpenVPN, Client** tab
- Click **plus** **Add to create a new client**
- Fill in the fields as follows, with everything else left at defaults:

See also

See [Client Configuration Options](#) for details on each of these options.

Description

Text to describe the connection (e.g. )

Server Mode

*Peer to Peer (SSL/TLS)*

DCO (Plus Only)

Check this box to activate the [OpenVPN Data Channel Offload \(DCO\)](#) feature for the client if desired.

See also

See [OpenVPN Data Channel Offload \(DCO\)](#) for additional information.

Device Mode

*tun*

Protocol

*UDP on IPv4 only*

Interface

*WAN*

Server host or address

The public IP address or hostname of the OpenVPN server ( in this example)

Server Port

Enable authentication of TLS packets

*Checked*

Automatically generate a shared TLS authentication key

*Unchecked*

TLS Key

Paste in the TLS key copied from the server instance

Peer Certificate Authority

The CA imported at the beginning of this process

Client Certificate

The client certificate imported at the beginning of this process

- Click Save

## Note

With remote access PKI configurations such as this example, routes and other configuration options are typically pushed from the server and thus not present in the client configuration. If the client side must reach additional networks, configure them in the **server** settings or a client-specific override as **Local Networks**.

# Firewall Rules

This next step is optional depending on whether or not hosts on the server network or other client sites need to initiate contact with hosts on the client network. If the other sites do not need to initiate contact with this client, then no action is necessary.

If the other sites needs to initiate contact, then this traffic requires a firewall rule on the **OpenVPN** tab on the *client* firewall to allow traffic from other VPN sites to reach the Client-side LAN. An “Allow all” style rule is OK in some cases, but a set of stricter rules is the best practice.

This example allows all traffic:

- Navigate to **Firewall > Rules, OpenVPN** tab
- Click **fa level up** **Add to create** a new rule at the top of the list
- Set the options as follows:

Protocol

*any*

Source

*any*

Tip

For extra security, create an alias containing only the remote hosts or subnets which must initiate contact with hosts on the client LAN, then use that alias as the source on this rule.

Destination

*any*

Tip

For extra security, create an alias containing only the local hosts or subnets on the client LAN which must accept connections from remote hosts across the VPN, then use that alias as the destination on this rule.

Description

Allow all on OpenVPN

- Click **Save**
- Click **Apply Changes**

# Testing the Connection

The configuration is now complete. The OpenVPN client instance automatically starts when created, so it should already be attempting to connect at this point and if the configuration is correct, it will be connected.

Try to ping across to the remote end LAN to verify connectivity.

# OpenVPN Remote Access Configuration Example

The OpenVPN wizard on pfSense® software is a convenient way to setup a remote access VPN for mobile clients. The wizard configures all of the necessary prerequisites for an OpenVPN remote access server:

- An authentication source (Local, RADIUS server, or LDAP server)
- A certificate authority (CA)
- A server certificate
- An OpenVPN server instance

At the end of the wizard the firewall will have a fully functioning sever, ready to accept connections from users. This server configuration can then be altered as needed.

This document uses an example setup to aide in explaining the options available in the wizard.

See also

[Server Configuration Options](#)

## Before Starting The Wizard

Before starting the wizard, plan the design of the VPN.

## Determine an IP addressing scheme

The OpenVPN server requires a dedicated subnet for communication between the server and the OpenVPN clients. This is the **Tunnel Network** in the server configuration. The server uses the first address in this subnet for itself to act as a gateway and it allocates IP addresses within this subnet to clients.

When selecting internal subnets for a single location, ideally choose subnets which can be CIDR summarized with other internal subnets. This example uses 10.3.0.0/24 for LAN and 10.3.201.0/24 for the remote access OpenVPN server. These two networks can be summarized with 10.3.0.0/16, which makes routing easier to manage.

See also

[CIDR Summarization](#)

# Example Network

Figure [OpenVPN Example Remote Access Network](#) shows a depiction of this example deployment.

The diagram shows the network configuration for an OpenVPN remote access server. It includes the WAN address (198.51.100.3), LAN subnet (10.3.0.0/24), LAN address (10.3.0.1), and tunnel network (10.3.201.0/24).

OpenVPN Example Remote Access Network

OpenVPN Remote Access Server Settings

Remote Access Server	
WAN Address	198.51.100.3
LAN Subnet	10.3.0.0/24
LAN Address	10.3.0.1
Tunnel Net	10.3.201.0/24

# OpenVPN Wizard Walkthrough

To start the OpenVPN Remote Access Server Setup wizard:

- Navigate to **VPN > OpenVPN**
- Click the **Wizards** tab

The GUI presents the first step of the wizard automatically

Note

The option for [OpenVPN Data Channel Offload \(DCO\)](#) is not included in this wizard. To use DCO on this server, run the wizard first then after completing the wizard, edit the server instance and enable the DCO option.

# Choose Authentication Type

On the first screen of the wizard, select the authentication backend server type. The choices available for **Type of Server** are *Local User Access*, *LDAP*, and *RADIUS*.

See also

## [Authentication Servers](#)

### Local User Access

Manage the users, passwords, and certificates using the [User Manager](#) on this firewall.

Sets the server mode to *Remote Access (SSL/TLS + User Auth)* which requires user authentication as well as per-user certificates.

*Local User Access* easily handles per-user certificates, managed completely in the GUI. This is much more secure, but depending on the number of users which will access the service, may be less convenient than using a central authentication system.

### LDAP / RADIUS

If the network has an existing authentication system already in place, such as Active Directory, pick *LDAP* or *RADIUS* depending on which method that system accepts.

*LDAP* and *RADIUS* both set the server mode to *Remote Access (User Auth)*, which does not require per-user certificates.

#### Note

The server mode can be adjusted later to require certificates, but administrators must manually create per-user certificates for *LDAP* or *RADIUS* users.

Click  **Next** to continue.


For *Local User Access*, the wizard skips the LDAP and RADIUS configuration steps.

For *LDAP* or *RADIUS* the wizard will present appropriate authentication server configuration options next. This example uses *Local User Access*, but this document discusses the other options for completeness.

# Choosing an LDAP Server

If the user manager configuration on this firewall contains one or more LDAP servers, the wizard offers these LDAP servers as options it can use for this VPN.

Click  **Add new LDAP server** to create a different LDAP server entry.

Click  **Next** to continue using the server selected in the **LDAP Servers** list.

If the firewall configuration does not contain any LDAP servers, the wizard skips this step.

See also

[Authentication Servers](#)

## Adding an LDAP Server

If the user manager configuration on this firewall does not contain an LDAP server, or if the user chose to create a new LDAP server, the wizard presents a screen to define a new server.

The values for the options on this screen depend on the specific LDAP directory configuration and structure. For guidance, consult the LDAP server administrator, software vendor, or documentation.

Note

The details of LDAP servers are covered in [LDAP Authentication Servers](#).

This document omits some detail since the options are discussed in-depth by that other section.

The wizard offers the following LDAP authentication server parameters:

Name

Descriptive name for this LDAP server, for reference.

Hostname or IP address

The hostname or IP address of the LDAP server.

If the firewall will contact this server using an encrypted method, this value must match the contents of the LDAP server certificate.

Port

The port on which the LDAP server is listening for requests.

The default port is 389 for standard TCP connections and 636 for SSL.

## Transport

Sets the method the firewall will use when performing LDAP queries to the server.

### Standard TCP

Unencrypted connections using plain TCP.

### STARTTLS Encrypted

Connects to the standard TCP port and then attempts to negotiate TLS encryption.

### SSL/TLS Encrypted

Secure connections using TLS encryption.

A standard TCP connection is typically sufficient for initial testing, and potentially for local servers or those only accessible over secure connections. If the server is remote or crosses any untrusted network links, an encrypted method is essential. Using an encrypted method is always the best practice, but may not always be viable.

## Warning

When the firewall uses an encrypted method to contact the LDAP server, the **Hostname or IP address** above must match a value in the LDAP server certificate.

## Peer Certificate Authority

To use SSL/TLS or STARTTLS transports, the firewall must trust the CA of the LDAP server. This can be accomplished by any of the following methods:

- Import the CA into the certificate manager and select it from the list in this option.
- Import the CA into the certificate manager with the **Trust Store** option set, which adds the imported CA into the list of CAs which the firewall trusts globally. Then select *global* from this list.
- If the LDAP server certificate is signed by a globally trusted CA, such as Let's Encrypt, then select *global*.

## Search Scope Level

Selects how deep the firewall will search in the LDAP directory, *One Level* or *Entire Subtree*.

In almost all cases, *Entire Subtree* is the correct choice.

## Search Scope Base DN

The distinguished name (DN) upon which the firewall bases its search. For example

DC=example,DC=com.

### Authentication Containers

These values specify where the directory stores user data. For example, CN=Users;DC=example.

### LDAP Bind User DN

If the LDAP server requires authenticated binds when performing queries, this field sets the distinguished name the firewall uses for this bind action.

If this is blank the firewall performs an anonymous bind without credentials.

### LDAP Bind Password

The password for authenticated binds. The firewall only uses this value if **LDAP Bind User DN** has a value.

### User Naming Attribute

Varies depending on the LDAP directory software and structure.

Typically cn for OpenLDAP and Novell eDirectory, and samAccountName for Microsoft Active Directory.

### Group Naming Attribute

Varies depending on the LDAP directory software and structure, but is most typically cn.

### Member Naming Attribute

Varies depending on the LDAP directory software and structure.

Typically member on OpenLDAP, memberOf on Microsoft Active Directory, and uniqueMember on Novell eDirectory.

See also


[LDAP Authentication Servers](#) explains the remaining options in detail, and when a server may require them.

Click  to go to the next page or type unknown **Add new server** to continue.

## Choosing a RADIUS Server

If the user manager configuration on this firewall contains one or more RADIUS servers, the wizard offers these RADIUS servers as options it can use for this VPN.

Click  **Add new RADIUS server** to create a different RADIUS server entry.

Click  **Next** to continue using the server selected in the **RADIUS Servers** list.

If the firewall configuration does not contain any RADIUS servers, the wizard skips this step.

See also

[Authentication Servers](#)

## Adding a RADIUS Server

If the user manager configuration on this firewall does not contain a RADIUS server, or if the user chose to create a new RADIUS server, the wizard presents a screen to define a new server.

The values for the options on this screen depend on the specific RADIUS configuration and structure. For guidance, consult the RADIUS server administrator, software vendor, or documentation.

### Note

The details of RADIUS servers are covered in [RADIUS Authentication Servers](#).

This document omits some detail since the options are discussed in-depth by that other section.

The wizard offers the following RADIUS authentication server parameters:

#### Name

Descriptive name for this RADIUS server, for reference.

#### Hostname or IP address

The hostname or IP address of the RADIUS server.

#### Authentication Port

Port used by the RADIUS server for accepting authentication requests, typically .

#### Shared Secret


The password the RADIUS server expects from this firewall when it submits authentication requests (e.g. password on the NAS entry.)

Click  **Add new server** to continue.

## Choosing a Certificate Authority

If the certificate manager configuration on this firewall contains one or more certificate authorities, the wizard offers these CA entries as options it can use for this VPN.

Click  **Add new CA** to create a different certificate authority.

Click  **Next** to continue using the certificate authority selected in the **Certificate authority** list.

If the firewall configuration does not contain any CA entries, the wizard skips this step.

See also

[Certificate Management](#)

## Creating a Certificate Authority

If the certificate manager configuration on this firewall does not contain a CA, or if the user chose to create a new CA, the wizard presents a screen to define a new CA.

See also

For more information on creating and managing CAs, see [Certificate Authority Management](#).

This document omits some detail since the options are discussed in-depth by that other section.

The firewall uses this entry as a root CA which can sign server and user certificates. Clients can use this CA to validate the server, and the server can use this CA to validate clients. Because this CA is self-signed, only clients which are supplied with a copy of this CA certificate will trust other certificates signed by this CA.

The wizard offers the following CA parameters:

Descriptive Name

ExampleCoCA

A name for reference to identify this certificate. This is the same as **Common Name** field for other certificates.

#### Note

Although this field can technically contain spaces, the best practice is to conform the contents of this field to the format allowed for fully qualified domain names.

Some clients have issues handling entries with spaces properly.

#### Key Length

2048

Size of the CA private key which the wizard will generate.

Larger keys offer increased security but larger keys are generally slower to use.

#### Lifetime

3650

The time, in days, for which this CA will remain valid.

For a self-signed CA such as this, the default of 3650 is acceptable, which is approximately 10 years.

The remaining fields are optional but define additional identifying data for the CA “subject”/distinguished name. For small deployments this may not matter much, but for larger organizations with CA entries at multiple sites, this can help ensure each CA is easily identifiable.

#### Country Code

US

(Optional) Two-letter ISO country code (e.g. US, AU, CA).

ExampleCo is located in the United States which has an ISO country code of US.

To locate an appropriate ISO code for other countries, use the [ISO Online Browsing Platform](#) site.

#### State or Province

Texas

(Optional) Full unabbreviated State or Province name (e.g. Texas, Indiana, California).

ExampleCo is located in .

City

(Optional) City or other Locality name (e.g. Austin, Indianapolis, Toronto).

ExampleCo headquarters is in .

Organization

(Optional) Organization name, often the Company or Group name.

Warning



Do not use any special characters in this field, not even punctuation such as a period or comma.

Click   **Add new CA** finish the CA creation process.

## Choosing a Server Certificate

If the certificate manager configuration on this firewall contains one or more certificates, the wizard offers these certificate entries as options it can use for this VPN.

Click   **Add new Certificate** to create a different certificate.

Click   **Next** to continue using the certificate selected in the **Certificate** list.

If the firewall configuration does not contain any certificate entries, the wizard skips this step.

See also

[Certificate Management](#)

## Adding a Server Certificate

If the certificate manager configuration on this firewall does not contain a certificate, or if the user chose to create a new certificate, the wizard presents a screen to define a new server certificate.

See also

For more information on creating and managing certificates, see [Certificate Management](#).

This document omits some detail since the options are discussed in-depth by that other section.

This server certificate verifies the identity of the server to the clients. The CA set in the previous wizard steps will sign this certificate. In most cases, as with this example, the server certificate uses the same information from the previous step and the wizard pre-fills the form automatically.

#### Descriptive Name

vpn.example.com

This is the common name (CN) field of the server certificate and the firewall also uses this name to reference the certificate.

The best practice is to set this to the fully qualified hostname of the firewall.

#### Note

Although this field can technically contain spaces, the best practice is to conform the contents of this field to the format allowed for fully qualified domain names.

Some clients have issues handling entries with spaces properly.

#### Key Length

2048

Size of the CA private key which the wizard will generate.

Larger keys offer increased security but larger keys are generally slower to use.

#### Lifetime

398

The time in days that this certificate will be valid. The best practice is to set this to 398 days or less.

#### Note

Some current operating systems and software limit server certificates to a maximum lifetime of 398 days for security reasons. Clients on these platforms may reject a server certificate with a longer lifetime.

The remaining fields are optional but define additional identifying data for the server certificate “subject”/distinguished name. For small deployments this may not matter much, but for larger organizations with many server certificates, this can help ensure each certificate is easily identifiable.

#### Country Code

US

(Optional) Two-letter ISO country code (e.g. US, AU, CA).

ExampleCo is located in the United States which has an ISO country code of US.

To locate an appropriate ISO code for other countries, use the [ISO Online Browsing Platform](#) site.

#### State or Province

Texas

(Optional) Full unabbreviated State or Province name (e.g. Texas, Indiana, California).

ExampleCo is located in Texas.

#### City

Austin

(Optional) City or other Locality name (e.g. Austin, Indianapolis, Toronto).

ExampleCo headquarters is in Austin.

#### Organization

ExampleCo

(Optional) Organization name, often the Company or Group name.

#### Warning

Do not use any special characters in this field, not even punctuation such as a period or comma.

Click  to go to field or type unknown **Create New Certificate** to continue.

## Configuring OpenVPN Server Settings

The options on this step of the wizard configure each aspect of how the OpenVPN server itself behave as well as options the server will pass on to clients.

See also

The options presented here are the same as those in [Server Configuration Options](#). Refer to that section for details.

Because the options are covered in detail in that section, this document only mentions the settings used by this example.

## General OpenVPN Server Information

These options control how the OpenVPN instance operates.

Interface

*WAN*

Protocol

*UDP on IPv4 Only*

Local Port

1194

The wizard suggests the first unused port number starting with port 1194. If there is an existing OpenVPN server on that port, use a different port number.

Description

ExampleCo Mobile VPN Clients

## Cryptographic Settings

These options control how the server encrypts and authenticates traffic in the tunnel.

TLS Authentication

Check **Enable authentication of TLS packets**

Using TLS authentication is the best practice.

Generate TLS Key

Check **Automatically generate a shared TLS authentication key**

TLS Shared Key

Blank

The wizard disables this field when **Automatically generate a shared TLS authentication key** is checked.

DH Parameters Length

2048

This value is a good balance of speed and strength.

Data Encryption Negotiation

*Checked*

This allows the server to automatically negotiate encryption settings with clients.

Note

Disabling this option is deprecated, but still present on this version for compatibility.

Data Encryption Algorithms

*AES-256-GCM, AES-128-GCM, and CHACHA20-POLY1305*

The best practice is to use the default suggested values as noted above.

Fallback Data Encryption Algorithm

*AES-256-CBC*

This algorithm is used when negotiation fails, for example with a client that is too old to support negotiation.

Auth Digest Algorithm

*SHA256 (256-bit)*

## Tunnel Settings

These options control how the server routes traffic from remote clients.

Tunnel Network

10.3.201.0/24

This is the tunnel network from the table at the start of this example ([OpenVPN Remote Access Server Settings](#)).

Redirect Gateway

*Unchecked*

For this example, The VPN will only carry traffic destined for subnets at the main office.

Local Network

10.3.0.0/24

This is the server-side LAN subnet from the table at the start of this example ([OpenVPN Remote Access Server Settings](#)).

Concurrent Connections

Blank

This example does not limit the number of clients which can connect at the same time.

Allow Compression

*Refuse any non-stub compression (Most secure)*

The best practice is to disable compression for security reasons.

Compression

*Disable Compression [Omit Preference]*

The best practice is to disable compression for security reasons.

Type-of-Service

*Unchecked*

There is no traffic on this example VPN which requires prioritization/QoS.

Inter-Client Communication

*Unchecked*

The clients on this VPN have no need to connect to other VPN client hosts.

Duplicate Connections

*Unchecked*

This example uses unique certificates for every client and does not allow multiple connections per client.

## Client Settings

These options control specific settings the server pushes to clients when they establish a connection.

### Dynamic IP

*Checked*

The clients connect from all over the country and unknown mobile networks and their IP addresses are likely to change without notice.

### Topology

*Subnet*

The method the server uses to assign IP addresses to clients.

### DNS Default Domain

example.com

The domain name used by ExampleCo.

### DNS Servers

10.3.0.5

A list of internal DNS servers. ExampleCo has a Windows Active Directory Domain Controller which is configured to act as a DNS server at 10.3.0.5.

### NTP Servers

10.3.0.6

A dedicated local NTP server exists at 10.3.0.6.

### Advanced

Blank

At this time no additional tweaks are necessary.

Click **Next** to continue.

# Firewall Rule Configuration

By default the firewall blocks all traffic from connecting to VPNs or passing over VPN tunnels. This step of the wizard adds firewall rules automatically to allow traffic to connect to the VPN and also so connected clients can pass traffic over the VPN.

Traffic from clients to server

Checked

When checked, the wizard adds a firewall rule on the chosen interface outside of the tunnel where the server is listening (e.g. *WAN*) which allows VPN clients to connect. The rule created by this option allows all clients from any source IP address to connect by default.

Since clients in this example are connecting from all over the country, the rule created by the wizard for this option is ideal.

Tip

To allow connections from a limited set of IP addresses or subnets, either make a custom rule or check this box and alter the rule it creates.

Traffic from clients through VPN tunnel

Checked

This setting allows all traffic to cross inside the OpenVPN tunnel. This is desirable for this example.

Click **Next** to continue.

# Finishing the Wizard

Click  to complete the wizard.

At this point, the firewall now contains a full OpenVPN remote access server configuration which is ready for client connections.

From here, the next steps are to add users and configure client devices.

If this setup requires adjustments to the automatically generated firewall rules, make them now.

# Verifying the Setup

Look at firewall rules (**WAN** and **OpenVPN** tabs)

- **WAN** tab rule should pass from any to the *OpenVPN* port on the *WAN address*

 /images/openvpn-ra-wanrule.png

- **OpenVPN** tab rule should allow all traffic from any/to any

 /images/openvpn-ra-ovpnrule.png

# Adjustments

Numerous settings are not present in the wizard but might be a better fit for certain deployments than the defaults chosen by the wizard.

## Server Mode

The OpenVPN **Server Mode** allows selecting a choice between requiring Certificates, User Authentication, or both. The wizard defaults to *Remote Access (SSL/TLS + User Auth)* when using local users and *Remote Access (User Auth)* for RADIUS and LDAP. The possible values for this choice and their advantages are:

### Remote Access (SSL/TLS + User Auth)

- Requires both certificates **and** username/password
- Each user has a unique client configuration which includes their personal certificate and key
- Most secure as there are multiple factors of authentication (TLS Key and Certificate that the user has, and the username/password they know)

### Remote Access (SSL/TLS)

- Certificates only, no authentication
- Each user has a unique client configuration which includes their personal certificate and key
- Useful if clients should not be prompted to enter a username and password
- Less secure as it relies only on something the user has (TLS key and certificate)

### Remote Access (User Auth)

- Authentication only, no certificates
- Useful if the clients cannot have individual certificates
- Commonly used for external authentication (RADIUS, LDAP)
- All clients can use the same exported client configuration and/or software package
- Less secure as it relies on a shared TLS key plus only something the user knows (Username/password)

## OpenVPN Data Channel Offload (DCO)

[OpenVPN Data Channel Offload \(DCO\)](#), a pfSense® Plus exclusive feature, can potentially increase performance of OpenVPN well beyond the capabilities of traditional OpenVPN connections.

### “ Note

OpenVPN DCO is generally stable but still under development.

OpenVPN DCO has been successful in many scenarios in lab and production environments, but there is still a small potential for instability or undesirable behavior.

Some OpenVPN features and use cases are not compatible with DCO. See [Limitations](#) for a list of known DCO limitations.

If a problem occurs with DCO, start a thread on the [Netgate Forum](#) to discuss and diagnose the issue.

## Certificate Revocation

Compromised certificates can be revoked by a Certificate Revocation List (CRL). CRL entries are managed at **System > Cert Manager** on the **Certificate Revocation** tab. Create a new CRL, add the certificate to it, and then select that CRL on the OpenVPN server settings.

See also: [Certificate Revocation List Management](#)

# Adding a User with a Certificate

If the server mode includes local user authentication, a user must exist in the user manager for each client which will connect to the VPN.

See also

This is a simplified version of the process. For more detail, see:

- [Adding OpenVPN Remote Access Users](#)
- [Manage Local Users](#)
- [User Certificates](#)

- Navigate to **System > User Manager**

- Click **fa-plus** **To add a user**

- Fill in the settings as follows:

Username

The username for this client.

Password/Confirm password

The password for this client.

Click to create a user certificate

*Checked*

Descriptive Name

Same value as the **Username**

Certificate Authority

The CA used by the OpenVPN server.

 **images/openvpn\_ra-usercert.png**

- Click **Save**

## OpenVPN Client Export Package

The OpenVPN Client Export Package can export client configurations formatted for a wide variety of platforms. It can also export a pre-packaged Windows installer executable which includes the configuration bundled inside for a painless client installation.

See also

# HaProxy

# T-RMM-PFSense-HAProxy-config

“ Assumes fully configured public DNS or DDNS, and a functional PFSense installation with existing valid wildcard SSL certificate available. Adjust hostnames, IPs, etc to suit the environment.

Do NOT disable nginx proxy on the T-RMM instance. This assumes that it's in place and functional.

- [HAProxy installation](#)
- [Firewall configuration](#)
- [HAProxy backend configuration](#)
- [Shared HTTP to HTTPS redirect frontend](#)
- [Shared HTTPS frontend](#)
- [T-RMM frontend](#)

# HAProxy installation

Go to System > Package Manager

Screenshot 2022-03-31 125739

Select Available Packages

Screenshot 2022-03-31 130058

Find and install haproxy-devel

Screenshot 2022-03-31 130322

Screenshot 2022-03-31 130322

# Firewall configuration

Go to Firewall > Rules

Screenshot 2022-03-31 135327

Select the WAN tab

Screenshot 2022-03-31 135621

Add the following two rules to the bottom of the list, nothing else should be using ports 80 and 443:

Screenshot 2022-03-31 135726

HTTP rule:

Screenshot 2022-03-31 140214

Create a duplicate rule, changing the port to 443 and the description for HTTPS

Enable the new rules.

# HAProxy backend configuration

Go to Services > HAProxy

Screenshot 2022-03-21 141001

Leave the Settings tab alone for now and skip to the Backend tab:

Screenshot 2022-06-22 122204

Add backend for rmm. Enter the rmm FQDN (eg, rmm.example.com) into the box titled Name, then click the down arrow in the Server list panel to add a server definition.

Enter the rmm for the server in the Name box, enter the internal IP address of the server, 443 (or other appropriate port) for the Port, and check the Encrypt(SSL) box.

In the Timeout / retry settings section, enter 30000 in Connection timeout and Server timeout.

In the Health checking section, set Health check method to none.

In the Advanced settings section, enter the following in the Backend pass thru box:

```
http-request add-header X-Forwarded-Host %[req.hdr(Host)]  
http-request add-header X-Forwarded-Proto https
```

Scroll down, save, and apply changes when asked.

rmmhaproxy5

Copy the rmm backend. Change the Name entry to match the mesh FQDN (eg, mesh.example.com).

Change the Name for the server to mesh.

In the Timeout / retry settings section, change the entries in Connection timeout and Server timeout to 15000.

In the Advanced settings section, add the following in the Backend pass thru box:

timeout tunnel 15000

Scroll down, save, and apply changes when asked.

Image not found or type unknown  
rmmhaproxy4

Copy the mesh backend. Change the Name entry to match the mesh FQDN-websockets (eg, mesh.example.com-websockets).

Change the Name for the server to mesh-websockets.

In the Timeout / retry settings section, change the entries in Connection timeout and Server timeout to **3000**.

In the Advanced settings section, change the timeout tunnel entry in the Backend pass thru box to **3600000**.

Scroll down, save, and apply changes when asked.

Image not found or type unknown  
Screenshot 2022-07-08 090956

Copy the mesh-websockets backend. Change the Name entry to match the rmm FQDN-websocket (eg, rmm.example.com-websocket).

Change the Name for the server to rmm-websocket.

In the Timeout / retry settings section, change the entries in Connection timeout and Server timeout to **30000**.

Scroll down, save, and apply changes when asked.

# Shared HTTP to HTTPS redirect frontend

Now go to the Frontend tab. Click the button to add a new frontend.

This shared http frontend will redirect all configured entries to their HTTPS equivalent and allow SSL offloading, as well as both internal and external access to the sites/services via URL.

Fill in the entries as shown in the screen capture below:

Screenshot 2022-03-31 144739

Scroll to the section titled "Default backend, access control lists and actions" and in the Action Control lists area click the down arrow to create a new acl. Enter **rmm** in the Name field, change the Expression to **Host matches**, and enter the FQDN for rmm into the Value field (eg, rmm.example.com).

Copy the rmm acl. Change the Name to **api**, and the Value field to the FQDN for api into the Value field (eg, api.example.com).

Copy the api acl. Change the Name to **mesh**, and the Value field to the FQDN for mesh into the Value field (eg, mesh.example.com).

Scroll down to the Actions area of the section and click the down arrow to create a new action. In the Action field, select **http-request redirect**, enter **scheme https** into the rule field, and enter **rmm** into the Condition acl names field.

Copy the action you just created, and change the Condition acl name to **api**.

Repeat this again, and change the Condition acl name to **mesh**.

Scroll down and select None for the Default Backend.

rmmhaproxy2 Copy

Scroll down to the Advanced settings section. Tick the **Use "forwardfor" option** box, select **http-server-close** for **Use "httpclose" option**, and add/copy-paste

http-request add-header X-Real-IP %[src]

to the Advanced pass thru text box.

Screenshot 2022-03-31 15:04:16

Save and apply changes.

# Shared HTTPS frontend

Click the button to add a new frontend.

Fill in the entries as shown in the screen capture below:

Screenshot 2022-03-31 15:18:54

No entries are necessary in the Default backend, access control lists and actions section, just make sure to set the Default Backend to None.

As before, scroll down to the Advanced settings section, tick the Use "forwardfor" option box, select http-server-close for Use "httpclose" option, and add/copy-paste

http-request add-header X-Real-IP %[src]

to the Advanced pass thru text box.

Next, scroll down to the SSL Offloading section. In the Certificate area, select the wildcard certificate for the domain and tick the box to Add ACL for certificate Subject Alternative Names.

In the OCSP area, tick the option box.

Screenshot 2022-03-31 15:28:41

Save and apply changes.

This shared HTTPS frontend will provide SSL offloading for ALL HTTPS frontends using it as a shared frontend, while allowing other ACLs and actions to be assigned to individual sub frontends independent from each other, as well as give a visual list of frontends/services that's easier to read than a long list of ACLs.

# T-RMM frontend

Click the button to add a new frontend.

Screenshot 2022-07-08 09:19:08  
Image not found or type unknown

## Action order matters!!!

In the Name field, enter **t-rmm**. In the Description field, enter the rmm FQDN (eg, rmm.example.com). Set the Status to active, tick the Shared Frontend box, and select **https\_shared - http** as the Primary frontend.

Scroll to the section titled "Default backend, access control lists and actions" and in the Action Control lists area click the down arrow to create a new acl. Enter **rmm** in the Name field, change the Expression to **Host matches**, and enter the FQDN for rmm into the Value field (eg, rmm.example.com).

Add a new acl. Change the Name to **nats-websocket**, set the Expression to **Path contains**, and enter **/natsws** as the Value.

Copy the rmm acl. Change the Name to **api**, and the Value field to the FQDN for api into the Value field (eg, api.example.com).

Add a new acl. Change the Expression to **Custom acl:** , in the Name field enter **is\_websocket** , and in the Value field enter **hdr(Upgrade) -i WebSocket** .

Copy the api acl. Change the Name to **mesh**, and the Value field to the FQDN for mesh into the Value field (eg, mesh.example.com).

Copy the api acl. Change the Name to **api-ws**, set the Expression to **Host contains**, and the Value field to the FQDN for api into the Value field (eg, api.example.com).

Scroll down to the Actions area of the section and click the down arrow to create a new action. In the Action field, select **Use Backend**, select the rmm backend you created earlier, and enter **rmm** into the Condition acl names field.

Copy the rmm action you just created, change the Condition acl name to **nats-websocket api-ws**, and change the backend to the rmm-websocket backend (eg, rmm.example.com-websocket).

Copy the initial rmm action you created, and change the Condition acl name to **api**.

Create a new action. In the Action field, select **Use Backend**, select the mesh websockets backend, and enter **is\_websocket mesh** into the Condition acl names field.

Copy the api action, select the mesh backend, and change the Condition acl name to **mesh**.

Scroll down and select None for the Default Backend.

Save and apply changes.

The websites/services should now be available internally and externally at the configured URLs, with SSL encryption, and automatic HTTP to HTTPS forwarding.

# How to Configure HAProxy for Docker-based Nextcloud AIO

## Purpose

Configure **HAProxy on pfSense** to terminate SSL and securely reverse-proxy public HTTPS traffic to an internal **Docker Nextcloud AIO server** behind your firewall.

---

## 1. HAProxy Package Installation on pfSense

On pfSense, go to:

- **System → Package Manager → Available Packages**
  - Search for **HAProxy** and install `haproxy` (not haproxy-devel unless needed).
- 

## 2. Create SSL Certificate (or Import)

In pfSense:

- **System → Certificate Manager → Certificates**
- Import or create an SSL certificate for your domain (example: `nextcloud.mydomain.com`).

---

## 3. HAProxy Settings

Go to **Services** → **HAProxy** and configure:

### Global Settings

- Enable HAProxy
- Set the SSL/TLS cipher suite to "Intermediate" (recommended for compatibility and security)

### Frontend (Public Side)

Name: frontend-https Bind address: WAN Address (or "any") Port: 443 Type: SSL Offloading (HTTPS) SSL Certificate: [Select imported Let's Encrypt or custom cert]

### Actions:

- **Condition:** Match on Host Header = nextcloud.mydomain.com
- **Action:** Use Backend: backend-nextcloud

### Optional:

- Add another frontend to redirect port 80 to 443 if you want forced HTTPS

---

## 4. HAProxy Backend (Internal Docker Host)

Name: backend-nextcloud Mode: HTTP (or HTTPS if you terminate SSL at the container) Server list: Name: nextcloud-docker Address: 192.168.100.19 Port: 11000 Health Check Method: HTTP-OPTIONS

# Important Backend Options:

- Check "Use HTTP/1.1"
- Forward host headers (preserve client IP)
- Add header X-Forwarded-Proto: https

## 5. Nextcloud Trusted Proxy Configuration

On the Nextcloud server, we modified the trusted proxies:

```
sudo docker exec -it nextcloud-aio-nextcloud bash cd /var/www/html/config nano config.php
```

Add or verify these lines inside `config.php`:

```
'trusted_proxies' => ['192.168.100.1'], 'overwritehost' => 'nextcloud.mydomain.com', 'overwriteprotocol' => 'https', 'overwrite.cli.url' => 'https://nextcloud.mydomain.com',
```

📌 Note: Replace `192.168.100.1` with your pfSense LAN IP if different.

## 6. Restart Docker Nextcloud Container

```
docker restart nextcloud-aio-nextcloud
```

## □ Summary

- pfSense HAProxy listens on WAN 443 (HTTPS)

- SSL terminated at pfSense, traffic forwarded to Docker Nextcloud Apache 11000
  - Client IP preserved using X-Forwarded-For headers
  - Nextcloud properly recognizes reverse proxy and HTTPS URL
- 

## Additional Notes

- HAProxy + pfSense reduces public attack surface on your Docker server
- Remember to update SSL certificates if using Let's Encrypt (can be automated)
- Use Health Checks to monitor Nextcloud availability
- Backup your pfSense HAProxy config after working setup